Setup InfluxDB on AWS EC2

Step 1. Install influxDB on AWS EC2

```
# connect to the EC2
# add influxdb repository key
sudo curl -sL https://repos.influxdata.com/influxdb.key | sudo apt-key add -
# create list file
sudo echo "deb https://repos.influxdata.com/ubuntu bionic stable" | sudo tee
/etc/apt/sources.list.d/influxdb.list
# install influxdb
sudo apt-get update && sudo apt-get install -y influxdb
# enable infliuxdb as a startup application
sudo systemctl enable --now influxdb
sudo systemctl restart influxdb
# configure influxdb
sudo nano /etc/influxdb/influxdb.conf
# uncomment enabled=true
[http]
# Determines whether HTTP endpoint is enabled.
enabled = true
# Determines whether the Flux query endpoint is enabled.
# flux-enabled = false
# then restart influxdb
sudo systemctl restart influxdb
sudo systemctl status influxdb
# create username and password
```

```
curl -XPOST "http://localhost:8086/query" --data-urlencode "q=CREATE USER
admin WITH PASSWORD <type_password_here> WITH ALL PRIVILEGES"
```

Step 2. Create database and load data

```
# type influx at the ec2 instance shell to enter the influx db shell
influx -username 'admin' -password 'your password here'

# And create a new database(tweet for instance) as below
> show databases
name: databases
name
----
_internal

> create database tweet
> show database
name: databases
name
----
_internal
tweet
```

To load the Nashville Tweet dataset into Influxdb, please execute the importer.ipynb notebook in this folder.

Step 3.: Install Chronograph on your Linux VM to run queries and visualize data from the influxDB.

Download and install Chronograph:

```
wget
https://dl.influxdata.com/chronograf/releases/chronograf_1.8.9.1_amd64.deb --
no-check-certificate
sudo dpkg -i chronograf_1.8.9.1_amd64.deb
```

Connect to the influxDB and view the data:

